



## **HAND HELD TERMINAL SETUP AND DOWNLOAD TO QUANTUM SYSTEM**

### **SETUP HAND HELD**

1. Connect the hand held to the PC
2. Turn the hand held on and select the START menu, then select QUANTUM
3. On the PC - From the Quantum system select the HAND HELD COLLECTION PROCESSING option from the COLLECTION tab
4. Select (tick) the site(s) and machine type(s) you wish to send to the hand held
5. Select the SETUP button – Quantum system will display message ENSURE HAND HELD IS READY TO CONNECT
8. On hand held – from the QUANTUM menu, select CONNECT TO PC then the RECEIVE option
9. On QUANTUM select the OK button
10. Records will be sent to hand held

### **DOWNLOAD FROM HAND HELD TO PC**

1. Connect the hand held terminal to the PC
2. Turn the hand held on and select the START menu, then select QUANTUM
3. On the PC – From the Quantum system select the HAND HELD COLLECTION PROCESSING option from the COLLECTION tab
4. Select (tick) the site(s) and machine type(s) you expect to receive from the hand held
5. Select the RECEIVE button – Quantum system will display message ENSURE HAND HELD IS READY TO CONNECT
8. On hand held – from the QUANTUM menu, select CONNECT TO PC then the TRANSFER option
9. On QUANTUM select the OK button
10. Records will be sent from hand held to PC